## How to use reporting alerts

## Overview

Our automated alerts feature notifies you of any processing irregularities with your merchant accounts. You decide what you would like to be notified about, as well as who should be notified. Alerts can be applied to individual merchants or an entire group.

## Available alerts include:

Purchase limit – a dollar amount for purchases

Return limit — a dollar amount for returns


Percentage keyed limit — the percentage of transactions keyed in the terminal

Batch close limit – the length of elapsed time since the last batch close

Idle time limit – the length of elapsed time since a terminal has been used

## Getting started


- 1. Go to: www.vantiv.com/merchant-resources/integrated-pos
- 2. Select MercuryView
- **3.** Login to the Portal on the upper right-hand side of the screen. If you don't know your password, click on the "Forgot Password" button to generate an email with your password. If you need to set up an account, contact Reseller Support at 1–800–846–4472, ext. 1820.



4. Click on "Alert Administration" under "Dealer Alerts" in the upper left-hand corner of the page.




5. Click on "Set Alerts Defaults" to get to the Dealer Alert Defaults page.




- **6.** The Dealer Alert Defaults page will allow you to view and change defaults for all of the available alerts for all of your merchant accounts. For example, you can designate all of your merchant accounts to have:
- · A Purchase Limit of \$1,500
- · A Return Limit of \$750
- · A Percentage Keyed Limit of 80%
- · A Batch Close Limit of 72 hours
- · An Idle Time Limit of 72 hours

7. To edit one of the dealer alert default settings for all of your accounts, choose the "edit" button. If you want to deactivate one of the default alert default settings for all of your accounts, choose the edit button.




- 8. If you choose to edit an alert setting, a new page will display options for you to:
- · change the default amount of the alert
- · deactivate the alert
- · choose what email you want the alert to be sent to
- · add a new email address

After making your selections, click "Configure Alerts" to return to the Dealer Alert Defaults page.



- 9. Continue this process for each alert you would like to edit or deactivate.
- **10.** After you are done choosing your global settings on the Dealer Alert Defaults page, you can customize alerts to individual merchants. To do so, click "OK" on the Dealer Alert Defaults page to continue.
- **11.** The next screen will allow you to edit the alerts for each individual merchant. You can view this page by merchants only, or by merchants and alerts.



Your reporting alerts activation is complete!

